How to Translate Aircast Into Other Languages

The graphical user interface of Aircast is in English, but can easily be translated into other languages using the techniques described in this document.

A couple of translation files (currently German and French) are included by default with each installation of Aircast. In the following you will learn how to create a translation file for another language.

How translation works


Aircast uses a Delphi port of the GNU gettext translation toolkit. When you start Aircast, it will determine the desired language is set up in the config (or use the default language of your Windows system), and then check if there is a translation file present for that language in the program folder. If this is the case, it will use the translations from that file instead of the English original every time a text is displayed somewhere.

- default.pot This is the so-called translation template. It contains the list of original English strings, but
 no translations. The template is supplied with each Aircast installation (since v4.4), and can be found in the
 Aircast program folder.
- Aircast.po This is the actual translation file that contains both the English strings and the translated strings. It must be located in a folder whose name matches the ISO code of the target language, see instructions below. The .po file is actually a text file, so you can open it in a text editor to explorer its contents. For editing it is recommended to use a special software though, e.g. poEdit, see below.
- Aircast.mo This is the compiled binary version of the .po file. It it generated automatically every time
 you save the .po file in poEdit. The application uses this binary .mo file because it allows faster access than
 the text file.

Preparing the translation

Locate translation template

Before we can start the translation, we first need to locate the translation template default.pot. It is included with every installtion of Aircast. Open Windows Explorer and navigate to the Aircast program folder, then go to the locale subfolder, and you should see it:



Create language folder


Inside the locale folder, you see a couple of subfolders, one for each translation that is already included by default: de (German), en_GB (British English), fr (French).

To start a new translation, you must first create a folder that matches the two-letter ISO 639-1 code of the language, e.g. da for Danish. For a list of all language codes see here: https://en.wikipedia.org/wiki/List of ISO 639-1 codes

If you're creating a translation for a special variant of a language for a particular country, you can also add the two-digit country code, separated by an underscore sign, to the language code, e.g. en_AR for Argentinian Spanish.


Important: Inside the "language code" folder you created, you must create another folder named LC_MESSAGES. This is where the translation file goes in the next step.

In the end it should look like this:



Copy and rename translation template

Finally we have to copy the translation template default.pot to our newly created LC_MESSAGES folder, and rename it to Aircast.po:




Now we're almost ready to start the translation.

Download and install poEdit

While .po files are plain text files and could be edited with any text editor, we recommend that you use a dedicated po file editor. Our favorite is *poEdit*, which is available for download here (the free version is fine, you don't have to pay for the Pro version if you don't want to): http://poedit.net/

When you're editing the Aircast.po file inside the Aircast program folder, it is necessary to run poEdit as Administrator, or you won't be able to save your work. To do so, adjust the security settings of poEdit.exe so that it always runs as Administrator:




(Sorry, no English screenshot available.)

Do the actual work

Having installed poEdit, you can double-click the Aircast.po file and poEdit will open it.

Set project name


The first time open the .po file, poEdit will display a message saying *Translation's project name isn't set*, and show a button *Set name* which displays the following dialog:



Enter *Aircast* as the project name, your name and e-mail as the team name/e-mail (it will give you the credits for the translation in the *About* dialog later), and both charsets to *UTF-8*. Then click *OK* to save.

Enter translations

Now you're ready to enter the translation strings. In the poEdit main window, there is a table that displays the English strings on the left, and the translations on the right (initially empty):




Click a line, and enter the translation into the text field at the bottom. You can now also use the arrow keys to move to the next string. Untranslated strings are in bold and at the top of the list, finished translations are in normal text and move down to the bottom when you save the file.


Remember to click Save once in a while to save your work!

However, Aircast must not be running at the time you save the translation in poEdit, because otherwise the .mo file cannot be written. If this is an issue for you, you can copy the Aircast.po and Aircast.mo files to another location, edit them from there, and copy them back to the LC_MESSAGES folder when you're done.

When you save the .po file, you will notice that poEdit also created the Aircast.mo file in the same folder:



So everything is in place now, and if the language is the same as your Windows language, Aircast should automatically detect and use the file. Otherwise run Aircast Configuration, go to $GUI \rightarrow General$, and set the language code accordingly:



Important hints

There are a couple of things that you have to take special care of when doing the translation.

Variables

You will notice that some of the English texts contain special placeholders starting with a % sign, like this:

Importing file %d of %d (%d errors). Estimated time remaining: %s

These are variables which will be filled with the actual text or data by Aircast. In particular, you will come accross the following placeholders:

- %d number
- %<format>f number with decimal point
- %s string/text

It is important that the translated text uses the exact same variables, in the exact same order! Otherwise software will crash later. For example, the above text would be translated to German like this:

Importiere Datei %d von %d (%d Fehler). Verbleibende Zeit: %s

Note that the variables %d, %d, %d, %s appear in the same order. Again, this is very important!

Quotation marks

Inside the .po file (remember that it's a text file) double quotes ("") are used to delimit the strings. Now when a double quote appears in one of the English strings, it will have a backslash (\) sign before it, to "escape" it:

\"A\" and \"B\" Buttons (left to right)

Again it is very important that you also use a backslash sign before any double quote in the translated text:

\"A\"- und \"B\"-Taster (links nach rechts)

New program versions

When you install a new version of Aircast, it may happen that there are new strings that must be translated. The installer will put a new default.pot file into the program folder. Your task is to merge that new template into your exisiting translation.

In order to do so, open your Aircast.po file in poEdit, then click $Catalogue \rightarrow Update from POT file$ from the menu. Select the new default.potfile and click Open.

poEdit will read the new template and add any new strings to your translation (and remove obsolete ones).

Sometimes poEdit will also make a **suggestion** based on your existing translations; these **fuzzy** translations are marked with a green star in the translation table. You can accept the suggestion by unchecking $Edit \rightarrow Translation$ is fuzzy in the menu, or pressing Ctrl+U. Or just enter a new one.

Make your translation available to the public

When you have finished a translation for a language that is not yet supported out of the box by Aircast, we will be happy to receive your translation files and included in the official distribution from now on.